


---

# InfoRad<sup>®</sup> SNPP-Connect<sup>™</sup>

InfoRad<sup>®</sup>, Inc.



InfoRad<sup>®</sup> and AlphaPage<sup>®</sup> are licensed registered trademarks of Information Radio Technology, Inc.  
SNPP-Connect<sup>™</sup> and AP<sub>32</sub><sup>™</sup> are trademarks of Information Radio Technology, Inc.

Copyright<sup>©</sup> 1985-2016 Information Radio Technology, Inc. All rights reserved. Printed in the United States of America. Except as permitted under the Copyright Act of 1976, no part of this publication may be reproduced or distributed in any form or by any means or stored in a database or retrieval system without prior written permission of the publisher.

rev. MD0116V151D1

# Table of Contents

Introduction .....	5
General Overview .....	5
Technical Overview .....	5
Installing InfoRad® SNPP-Connect™ .....	6
SNPP-Connect™ Configuration .....	11
Utilities menu .....	17
Using InfoRad® SNPP-Connect™ With InfoRad® Watch-IT ASCII SV and InfoRad® Enterprise SV* .....	18
Using InfoRad® SNPP-Connect™ With InfoRad® Watch-IT Serial .....	21
Troubleshooting InfoRad® SNPP-Connect™ .....	23
SNPP-Connect Manual Install / Uninstall.....	24
Technical Support .....	25
License Agreement.....	26
Copyright.....	27



# Introduction

---

## InfoRad® SNPP-Connect™

---

### General Overview

The InfoRad® SNPP-Connect™ Gateway is a powerful frontend software solution that will process incoming SNPP messages directly through the InfoRad Wireless Enterprise SV\*, InfoRad Watch-IT ASCII SV, or InfoRad Watch-IT Serial messaging software. Incorporating the SNPP-Connect™ Gateway adds additional capability and versatility to your messaging environment while maintaining a high level of control, security, and reliability over your enterprise messaging network.

### Technical Overview

The InfoRad SNPP-Connect™ Gateway output is monitored by InfoRad Enterprise SV\*, Watch-IT ASCII SV, or InfoRad Watch-IT Serial software for an incoming SNPP message. Upon detection and confirmation of a valid address, the message or messages are dispatched to the intended receivers. The InfoRad software will validate, direct and or redirect and log all message transactions to the designated carriers including private systems.

When integrated with the InfoRad Enterprise SV\* or Watch-IT ASCII SV software the incoming SNPP address to the gateway can be assigned to an individual receiver or group of receivers within the InfoRad Enterprise SV\* or Watch-IT ASCII SV software.

When integrated with the InfoRad Watch-IT Serial software the incoming SNPP message is parsed for an alarm code or key word(s) and sent to the assigned Receiver(s) or Group(s) programmed to receive messages for the alarm code or key word(s).


Outgoing multiple message protocol support and Route-on-Failure are provided via SNPP, WCTP, SMTP, TAP, including direct serial TAP. InfoRad SV software runs under MS Windows as a Service. If using InfoRad v10.4.0 or later, select SMS providers are supported.

**\*Note:** The InfoRad Enterprise SV software requires a 10-Client license or greater.


---

## Installing InfoRad® SNPP-Connect™


1. Make a back-up copy of your InfoRad SNPP-Connect™ disk or download file.
2. The Setup should start automatically from CD to install InfoRad® SNPP-Connect™ on your computer hard drive, or run the Setup file located on the CD or in the download files.
3. The InfoRad® SNPP-Connect™ InstallShield Wizard will appear. Click on the Next button or press Return to continue the installation of InfoRad® SNPP-Connect™





4. The InfoRad® SNPP-Connect™ InstallShield Wizard license agreement screen will appear. Select the “I accept...” option and click on the Next button to continue the installation of InfoRad® SNPP-Connect™.




5. You are then prompted for a destination directory for the installation. If you wish to change the directory where the InfoRad® SNPP-Connect™ application will be installed, click on the Change button and select a new directory. Otherwise, click on the Next button to continue the installation process.



6. Ready to Install! Click Install button and setup will then install the program files.




7. Click on Finish



# SNPP-Connect™ Configuration

Once the program files are installed, the InfoRad® SNPP-Connect™ Configuration application will start.




If you are evaluating InfoRad® SNPP-Connect™ in Demo mode, please continue to the next page to complete Configuration settings.


If you have purchased InfoRad® SNPP-Connect™, enter your license number:

From the Menu bar select **Licensing**.

Enter your license number and then click the Save button.



To configure InfoRad® SNPP-Connect™, click on the **Edit settings** button.



**SNPP server port field:** Enter the port number you want InfoRad® SNPP-Connect™ to monitor for SNPP input.

**Output mode:** Select 'Message file' if SNPP-Connect™ is to be used with InfoRad Enterprise SV\* or InfoRad Watch-IT ASCII SV; select 'Serial port' if SNPP-Connect™ is to be used with InfoRad Watch-IT Serial.

**Output directory field:** enter the path to your InfoRad Enterprise SV, InfoRad Watch-IT ASCII SV message directory, or enter the path to your InfoRad Watch-IT Serial directory. For example, if the default installation path was used:

InfoRad V10.4.0 and later:

InfoRad Enterprise SV: C:\ProgramData\InfoRad\InfoRad Enterprise SV Service\MSG\

Watch-IT ASCII SV: C:\ProgramData\InfoRad\InfoRad Watch-IT ASCII SV Service\MSG\

Watch-IT Serial: C:\ProgramData\InfoRad\InfoRad Watch-IT Serial\

InfoRad V10.3.8 and previous:


InfoRad Enterprise SV: C:\Program Files\InfoRad Enterprise SV Service\MSG\

Watch-IT ASCII SV: C:\Program Files\InfoRad Wireless Watch-IT ASCII SV Service\MSG\

Watch-IT Serial: C:\Program Files\InfoRad Wireless\


**Note:** please include the trailing backslash in the path

**Logging option:** Turn on the logging option for troubleshooting. The InfoRad® SNPP-Connect™ service will place the log file in a folder named **Logs** in the **Output directory**. The log file is a text file and will be named with the date. (Ex: 08\_25\_1014.txt)



If using InfoRad Enterprise SV or InfoRad Watch-IT ASCII SV click the **Save Changes** button to save your settings.

If using InfoRad Watch-IT Serial click on 'Serial port' tab for serial port settings.



**NOTE: Serial port settings should match those in Watch-IT Serial – Serial Monitoring Setup**

**Com number:** enter the Comport number for SNPP-Connect serial data output

**Data rate:** select data rate from the dropdown list: 300, 1200, 2400, 4800, 9600, 19200, 38400

**Parity:** select parity setting from the dropdown list: Even, Odd, None

**Data bits:** enter 7 or 8 data bits

**Stop bits:** enter 1 or 2 stop bits

**Flow Control:** select flow control from dropdown list: Hardware, Software, None

**End string:** enter the end of string /end of data character(s)

**Supported characters:**

\r carriage return (must be lowercase 'r')

\n new line (line feed) (must be lowercase 'n')

\xy any 2 hex characters (Example: \04 for EOT)

If none of the above, then enter a character string (Example: END or end)


Click the **Save Changes** button to save your settings.

## Utilities menu

**Delete Status files option:** (default) The InfoRad® SNPP-Connect™ service will delete InfoRad Message Status files after processing. (InfoRad Enterprise SV or InfoRad Watch-IT ASCII SV only)

**Save Status files option:** Select this option to save InfoRad Message Status files for troubleshooting purposes. Error status files contain error statements when message send attempts fail. (InfoRad Enterprise SV or InfoRad Watch-IT ASCII SV only)

**Search New license option:** This option allows the InfoRad® SNPP-Connect™ service to find a new InfoRad License number. For example, if the InfoRad® SNPP-Connect™ service was initially setup in Demo mode (30-day Trial mode) with a 30-day Trial version of Enterprise SV or Watch-IT ASCII SV, once the full version of InfoRad product is installed you can license the InfoRad® SNPP-Connect™ from Demo to licensed mode by using Search New license, and then entering the InfoRad® SNPP-Connect™ license number under the Licensing menu.



---

## Using InfoRad<sup>®</sup> SNPP-Connect<sup>™</sup> With InfoRad<sup>®</sup> Watch-IT ASCII SV and InfoRad<sup>®</sup> Enterprise SV\*

The InfoRad SNPP-Connect<sup>™</sup> runs as a service under MS Windows and monitors a designated **SNPP server port** for SNPP traffic for valid incoming messages. The InfoRad<sup>®</sup> SNPP-Connect<sup>™</sup> service processes the SNPP data for sending and formats the message for the InfoRad Wireless Watch-IT ASCII SV or InfoRad Wireless Enterprise SV\* software to redirect the message using supported wireless industry messaging protocols.

When the InfoRad<sup>®</sup> SNPP-Connect<sup>™</sup> receives an incoming SNPP message it parses the receiver information and the message text from the SNPP data.

The receiver information is then used as the recipient name within the InfoRad Watch-IT ASCII SV and Enterprise SV\* software; therefore, **the receiver number or name must exist in the InfoRad Watch-IT ASCII SV or Enterprise SV\* software program database as a Receiver name or Group name.** For example, “PaulCell” or “2165311369” would be entered in the InfoRad program as a Receiver or Group name. (See next page for example database entries.)

The SNPP message text is used for the message text for the InfoRad program.

When the InfoRad program receives a message that has been processed by InfoRad<sup>®</sup> SNPP-Connect<sup>™</sup>, the message is sent to the Receiver or Group name using the appropriate phone number(s) and Messaging Service(s) as defined in the InfoRad program database. Outgoing multiple message protocol support and route-on-failure are provided via SNPP, WCTP, SMTP, TAP, including direct serial TAP. If using InfoRad v10.4.0 or later, select SMS providers are supported.

**\*Note:** The InfoRad Enterprise SV software requires a 10-Client license or greater.

## Example database entries in InfoRad Wireless Watch-IT ASCII SV or InfoRad Wireless Enterprise SV:

- 1) Using phone number in SNPP messages. Systems generating SNPP messages typically use the phone number. For example, using a phone number of <2165311369> to send to an employee phone or pager via SNPP-Connect, enter a Receiver Name of 2165311369 in the InfoRad database:

**Wireless Receiver Setup**

Name of person carrying this receiver:  
2165311369

Receiver's ID number or E-mail address:  
2165311369

Encryption: None

Encryption key:

Messaging Service:  
Verizon Wireless -EM WCTP Secur

Log messages to this receiver on my hard disk

Route on Failure

Route to alternate receiver

Alternate receiver's ID number or E-mail address:

Messaging Service:  
1and1 - Email SMTP

Buttons: OK, Cancel, Use Wizard, Help

When an SNPP message to <2165311369> is captured by SNPP-Connect, the result is the text of the SNPP message will be sent to the wireless receiver defined as '2165311369' in the InfoRad Receiver database.

Note: SNPP-Connect will strip dashes, spaces, and dots from the phone number submitted by the external SNPP system. Therefore you should NOT include dashes, spaces, or dots in the number for the Receiver name in the InfoRad database.

- 2) Using name in SNPP messages. If your system generating SNPP messages uses or allows text names (vs phone numbers), SNPP-Connect supports text names\*. For example, using an SNPP receiver address of <PaulCell> to send to Paul's cell phone via SNPP-Connect, enter a Receiver Name of PaulCell in the InfoRad database:

The screenshot shows a 'Wireless Receiver Setup' dialog box with the following fields and options:

- Name of person carrying this receiver: PaulCell
- Receiver's ID number or E-mail address: 2165551212
- Messaging service: Verizon Wireless - EM WCTP
- Log messages to this receiver on my hard disk
- Route on Failure:
  - Route to alternate receiver
  - Alternate receiver's ID number or E-mail address: (empty)
  - Messaging Service: ABeep - Internet SNPP

When an SNPP message to <PaulCell> is captured by SNPP-Connect, the result is the text of the SNPP message will be sent to the wireless receiver defined as PaulCell in the InfoRad Receiver database.

\*Note: SNPP-Connect will strip dashes, spaces, and dots from the text name submitted by the external SNPP system. Therefore you should NOT include dashes, spaces, or dots in the name for the Receiver in the InfoRad database. (If your external SNPP system allows, underscores in names are permissible. Ex: Paul\_Cell )

---

## Using InfoRad® SNPP-Connect™ With InfoRad® Watch-IT Serial

The InfoRad SNPP-Connect™ runs as a service under MS Windows and monitors a designated **SNPP server port** for SNPP traffic for valid incoming messages. The InfoRad® SNPP-Connect™ service processes the SNPP data for sending and formats the message for the InfoRad Wireless Watch-Serial software to redirect the message using supported wireless industry messaging protocols.

When the InfoRad® SNPP-Connect™ receives incoming SNPP data it parses the SNPP message text from the SNPP data which is then output via the assigned serial port to the InfoRad Watch-IT Serial software.

The Watch-IT Serial software receives the SNPP message text that has been processed by InfoRad® SNPP-Connect™, and parses the incoming SNPP message text for programmed alarm code or key word(s). Watch-IT Serial then sends the SNPP message text and / or optional ‘additional text’ to the assigned Receiver(s) or Group(s) programmed within the Watch-IT Serial software to receive messages for the specific alarm code or key word(s) using the appropriate phone number(s) and Messaging Service(s) as defined in the InfoRad program database.

Outgoing multiple message protocol support and route-on-failure are provided via SNPP, WCTP, SMTP, TAP, including direct serial TAP. If using InfoRad v10.4.0 or later, select SMS providers are supported.

### Sample Watch-IT Serial Code setup:

Example for alarm code / key word(s) containing “ALARM407”

When an input record containing this alarm code arrives:

ALARM407

Alarm code starts  at column   anywhere

Send an alert message that includes:

record text from column 1 to column 80


additional record text from column 1 to column 1

additional text: FIRE ALARM Room 407


the date and time

OK Cancel

Assign code to FIRE ALARM GROUP



FIRE ALARM GROUP created in Watch-IT Serial Group database



Using the above settings, when “ALARM407” is triggered the result is Watch-IT Serial will send the text message “ALARM407 FIRE ALARM ROOM 407” to the wireless receivers for John and Mike (as defined in the InfoRad Receiver database).

---

# Troubleshooting InfoRad® SNPP-Connect™

## SNPP-Connect logging:

In the InfoRad® SNPP-Connect™ Configuration application turn on the **Logging** option and in the **Utilities** menu select **Save Status** files (when using InfoRad Wireless Watch-IT ASCII SV or InfoRad Wireless Enterprise SV). The InfoRad® SNPP-Connect™ log file can be used to view the SNPP message input. The InfoRad® SNPP-Connect™ service will place the log file in a folder named **Logs** in the **Output directory** defined in the SNPP-Connect Configuration application. The log file is a text file and will be named with the date. (Ex: 08\_25\_2014.txt).

## Enterprise SV and Watch-IT ASCII SV message status logs:

InfoRad Wireless Watch-IT ASCII SV or InfoRad Wireless Enterprise SV program message status files can be used to find processing or sending problems. Message log files are found in the Message Directory (the **Output directory** defined in the SNPP-Connect Configuration application). Messages with errors will create an Error Status File named with the format ERR\_MSG\_\_viaSNPPC.*nnn* (*nnn* = message number).

Utilizing Message Status Files along with Internet and/or Communications diagnostic log files (discussed next) will further aid troubleshooting.

## Internet, modem, and direct serial connection diagnostic logs:

Diagnostic logging options for Internet messaging protocols are found in the Enterprise SV, Watch-IT ASCII SV, and Watch-IT Serial programs under the program Internet Settings Setup. The Internet diagnostic log file, named “inetlog.txt”, is found in the program folder\*.

Diagnostic logging options for Dial-up TAP (Modem) and Direct Serial Connection communications are found in the Enterprise SV, Watch-IT ASCII SV, and Watch-IT Serial programs under the program Communications Settings Setup. The Communications diagnostic log files are found in the program folder\*. Modem or Direct Serial Connection log files are named with the format CMddhhmm.TXT. (Example: for a message attempted on the 19<sup>th</sup> at 11:32 am the log file will be named CM191132.TXT.)

## Watch-IT Serial – serial port input diagnostic logs:

InfoRad Wireless Watch-IT Serial: Serial port diagnostic log files (option found in Serial Monitoring Setup) can be used to log incoming serial data. Two kinds of serial data log files are created for serial diagnostics and both can be found in the program folder\*. “Simlog.txt” is a continuous log in a more readable format. Additionally, there are log files with the format “SMddhhmm.TXT” that are a raw data log that is created for each serial session. (Example: if the program is started or Serial Monitoring is started on the 19<sup>th</sup> at 11:32 am, the session log will be named SM191132.TXT. )

**Note:** When finished troubleshooting, turn off diagnostic logging options in the associated programs, and delete any existing diagnostic log files.

\*InfoRad program diagnostic logs are located in the ProgramData folder for v10.4.0 and later.

---

## SNPP-Connect Manual Install / Uninstall

If you have any trouble with the Windows Installer you can manually install the SNPP-Connect service and configuration application.

If you have attempted to use the Windows Installer previously, you should first uninstall the SNPP-Connect. You can attempt to do that from the Windows Add/Remove Programs utility.

If you cannot uninstall from Add/Remove Programs then go to the Command prompt (Start menu – Run or Accessories then Run) and run:

```
sc delete ir_snpp_connect  
(you may have to go to the System folder that contains the sc command and then run the command – EX:  
C:\Windows\System32)
```

You should then re-boot the machine.

### **To manually install the service:**

On the installation CD go to the “Manual Install Files” folder and copy the files to your desired program folder (EX: C:\SNPP-Connect).

Again go to the Command prompt and run:

```
[InstallDirectory] IRsnppSrv.exe /INSTALL
```

Example:

```
C:\SNPP-Connect\IRsnppSrv.exe /INSTALL
```

Once installed you can start the service at the Command prompt:

```
sc start ir_snpp_connect  
(you may have to go to the System folder that contains the sc command and then run the command – EX:  
C:\Windows\System32)
```

Or you can start the service from the Services Control Panel.

Once the service is running, create a shortcut on the desktop to the “IRsnppConnect.exe” in the installation folder.

Start the “IRsnppConnect.exe” and proceed with License and Setup per the manual instructions.

---

# Technical Support

Technical Support is only available to registered users of the software as detailed in the licensing agreement. Please register if you haven't already.

This program is licensed with 90 days free telephone technical support included. AlphaCare Subscription options are available that extend the support period, as well as offer priority telephone support and Upgrade Protection. Out-of-warranty support is also available on a per-incident basis.

Please call InfoRad Sales at (800) 228-8998 for details on AlphaCare, or email to [sales@inforad.com](mailto:sales@inforad.com), or see our website at [www.inforad.com](http://www.inforad.com).

InfoRad Software Technical Support is available Monday through Friday 8:30–5:30 ET.

Optional Extended Support Services weekend/holiday and 24x7 options available.

A technical support section with solutions to common problems is also available at [www.inforad.com/techsupport](http://www.inforad.com/techsupport)

Phone:	(216) 531-1369
Email:	<a href="mailto:techsupport@inforad.com">techsupport@inforad.com</a>
Internet:	<a href="http://www.inforad.com">www.inforad.com</a>

---

# License Agreement

## InfoRad® SNPP-Connect™

Read this agreement carefully before using this package. Use of this package by you or your agent, including your employee, means that you accept the terms of this License Agreement. If you do not agree to the terms of this license agreement, promptly return this package. A refund is issued only if you have removed all the associated software files related to this package from your computer system and have destroyed all backup copies before returning the software. Your money will be refunded if you have honored the above stated refund terms and the package is returned within 30 days of purchase. If a demonstration version has been supplied, it in addition to the terms stated in this agreement is not for sale or copy. The demonstration version is supplied solely for demonstrating the products features and ability to operate.

This License Agreement licenses the use of this product for the United States of America only. No use beyond the United States of America is authorized by this agreement or by the purchase of this product.

InfoRad SNPP-Connect is licensed for use ONLY with the following InfoRad products:

InfoRad Enterprise SV (10-Client License and greater)  
InfoRad Watch-IT ASCII SV  
InfoRad Watch-IT Serial

### THE LICENSEE IS ENTITLED TO:

- A. Use one copy of the licensed program on a single machine with a single CPU at a single site unless this software has been purchased with a multi-user SITE or LAN license;
- B. Remove the licensed program from one computer and install it on another. At no time is it permitted to make multiple copies for others to use or transfer the program license except under the terms set forth within this agreement;
- C. Make one copy of the software solely for backup purposes;
- D. Transfer the program and license to another party so long as the other party agrees to the terms and conditions of this Agreement, and written notification is given to Information Radio Technology, Inc. of said transfer. If the program is transferred, all copies not transferred, whether in machine readable or printed form must be destroyed. This includes all modifications and portions of the program used;
- E. Use the manual for its intended purpose by the licensee or his agents.
- F. Telephone Technical Support for 90 days for registered users.

### THE LICENSEE IS PROHIBITED FROM:

- A. Using, modifying, copying or in any way transferring, by any means or medium the licensed program except as expressly permitted by this Agreement or by prior written agreement of Information Radio Technology Inc.;
- B. Distributing, renting, giving, lending, sub-licensing or leasing, disseminating, translating, reverse engineering, decompiling, disassembling and/or creating derivative works from the licensed program;
- C. Using or allowing use of the backup copy unless the purchased diskette becomes defective;
- D. Copying the manual or using the manual except as authorized.

---

## Copyright

The software is licensed to you for your use, the software is not sold to you. The software and documentation is owned by Information Radio Technology, Inc., and is protected by the copyright laws of the United States and by international treaties.

You must reproduce and include the copyright notice on any backup copy. Any copy of the software made by you will be the property of Information Radio Technology, Inc. and is subject to the terms and conditions of this agreement.

This license agreement terminates with the licensed purchaser or user upon transfer of this program or for failure to comply with the terms of this Agreement. Upon termination, the licensee has no rights to use this program and must destroy all copies in his or her possession.

Information Radio Technology, Inc. retains all rights not expressly granted by this Licensee Agreement. This Agreement constitutes the complete and exclusive Agreement between the parties.